

**DNYANSAGAR ARTS AND COMMERCE COLLEGE,
BALEWADI,PUNE-45**



2013 PATTERN
SUBJECT: OPERATING SYSTEM
SUB CODE: CA-403
CLASS: TYBBA(CA) SEM-VI

By :Prof Tejashri M.

www.dacc.edu.in



UNIT 1

Introduction to OS



What is an Operating System?

- A program that acts as an intermediary between a user of a computer and the computer hardware.
- Operating system goals:
 - Execute user programs and make solving user problems easier.
 - Make the computer system convenient to use.
- Use the computer hardware in an efficient manner.




Computer System Components

1. Hardware – provides basic computing resources (CPU, memory, I/O devices).
2. Operating system – controls and coordinates the use of the hardware among the various application programs for the various users.
3. Applications programs – define the ways in which the system resources are used to solve the computing problems of the users (compilers, database systems, video games, business programs).
4. Users (people, machines, other computers).



Abstract View of System Components





Operating System Definitions

- Resource allocator – manages and allocates resources.
- Control program – controls the execution of user programs and operations of I/O devices .
- Kernel – the one program running at all times (all else being application programs).




Mainframe Systems

- Reduce setup time by batching similar jobs
- Automatic job sequencing – automatically transfers control from one job to another.
First rudimentary operating system.
- Resident monitor
 - initial control in monitor
 - control transfers to job
 - when job completes control transfers back to monitor




Memory Layout for a Simple Batch System





Multiprogrammed Batch Systems

Several jobs are kept in main memory at the same time, and the CPU is multiplexed among them.





OS Features Needed for Multiprogramming

- I/O routine supplied by the system.
- Memory management – the system must allocate the memory to several jobs.
- CPU scheduling – the system must choose among several jobs ready to run.
- Allocation of devices.



Time-Sharing Systems–Interactive Computing

- The CPU is multiplexed among several jobs that are kept in memory and on disk (the CPU is allocated to a job only if the job is in memory).
- A job swapped in and out of memory to the disk.
- On-line communication between the user and the system is provided; when the operating system finishes the execution of one command, it seeks the next “control statement” from the user’s keyboard.
- On-line system must be available for users to access data and code.



Desktop Systems

- *Personal computers* – computer system dedicated to a single user.
- I/O devices – keyboards, mice, display screens, small printers.
- User convenience and responsiveness.
- Can adopt technology developed for larger operating system' often individuals have sole use of computer and do not need advanced CPU utilization of protection features.
- May run several different types of operating systems (Windows, MacOS, UNIX, Linux)



Parallel Systems

- Multiprocessor systems with more than one CPU in close communication.
- *Tightly coupled system* – processors share memory and a clock; communication usually takes place through the shared memory.
- Advantages of parallel system:
 - Increased *throughput*
 - Economical
 - Increased reliability
 - graceful degradation
 - fail-soft systems




Parallel Systems (Cont.)

- *Symmetric multiprocessing (SMP)*
 - Each processor runs an identical copy of the operating system.
 - Many processes can run at once without performance deterioration.
 - Most modern operating systems support SMP
- *Asymmetric multiprocessing*
 - Each processor is assigned a specific task; master processor schedules and allocates work to slave processors.
 - More common in extremely large systems



Symmetric Multiprocessing Architecture





Distributed Systems

- Distribute the computation among several physical processors.
- *Loosely coupled system* – each processor has its own local memory; processors communicate with one another through various communications lines, such as high-speed buses or telephone lines.
- Advantages of distributed systems.
 - Resources Sharing
 - Computation speed up – load sharing
 - Reliability
 - Communications




UNIT 2

System Structure



Computer-System Architecture





Computer-System Operation

- I/O devices and the CPU can execute concurrently.
- Each device controller is in charge of a particular device type.
- Each device controller has a local buffer.
- CPU moves data from/to main memory to/from local buffers
- I/O is from the device to local buffer of controller.
- Device controller informs CPU that it has finished its operation by causing an *interrupt*.



Common Functions of Interrupts

- Interrupt transfers control to the interrupt service routine generally, through the *interrupt vector*, which contains the addresses of all the service routines.
- Interrupt architecture must save the address of the interrupted instruction.
- Incoming interrupts are *disabled* while another interrupt is being processed to prevent a *lost interrupt*.
- A *trap* is a software-generated interrupt caused either by an error or a user request.
- An operating system is *interrupt driven*.




Interrupt Handling

- The operating system preserves the state of the CPU by storing registers and the program counter.
- Determines which type of interrupt has occurred:
 - *polling*
 - *vectored* interrupt system
- Separate segments of code determine what action should be taken for each type of interrupt



Interrupt Time Line For a Single Process Doing Output





I/O Structure


- After I/O starts, control returns to user program only upon I/O completion.
 - Wait instruction idles the CPU until the next interrupt
 - Wait loop (contention for memory access).
 - At most one I/O request is outstanding at a time, no simultaneous I/O processing.
- After I/O starts, control returns to user program without waiting for I/O completion.
 - *System call* – request to the operating system to allow user to wait for I/O completion.
 - *Device-status table* contains entry for each I/O device indicating its type, address, and state.
 - Operating system indexes into I/O device table to determine device status and to modify table entry to include interrupt.



Two I/O Methods


Synchronous

Asynchronous





Device-Status Table





Direct Memory Access Structure

- Used for high-speed I/O devices able to transmit information at close to memory speeds.
- Device controller transfers blocks of data from buffer storage directly to main memory without CPU intervention.
- Only one interrupt is generated per block, rather than the one interrupt per byte.




Storage Structure

- Main memory – only large storage media that the CPU can access directly.
- Secondary storage – extension of main memory that provides large nonvolatile storage capacity.
- Magnetic disks – rigid metal or glass platters covered with magnetic recording material
 - Disk surface is logically divided into *tracks*, which are subdivided into *sectors*.
 - The *disk controller* determines the logical interaction between the device and the computer.



Moving-Head Disk Mechanism






Storage Hierarchy

- Storage systems organized in hierarchy.
 - Speed
 - Cost
 - Volatility
- *Caching* – copying information into faster storage system; main memory can be viewed as a last *cache* for secondary storage.



Storage-Device Hierarchy






Caching

- Use of high-speed memory to hold recently-accessed data.
- Requires a *cache management* policy.
- Caching introduces another level in storage hierarchy. This requires data that is simultaneously stored in more than one level to be *consistent*.



Migration of A From Disk to Register





Hardware Protection

- Dual-Mode Operation
- I/O Protection
- Memory Protection
- CPU Protection



UNIT 3

Process Management



Process Concept

- An operating system executes a variety of programs:
 - Batch system – jobs
 - Time-shared systems – user programs or tasks
- Textbook uses the terms *job* and *process* almost interchangeably.
- Process – a program in execution; process execution must progress in sequential fashion.
- A process includes:
 - program counter
 - stack
 - data section




Process State

- As a process executes, it changes *state*
 - **new**: The process is being created.
 - **running**: Instructions are being executed.
 - **waiting**: The process is waiting for some event to occur.
 - **ready**: The process is waiting to be assigned to a process.
 - **terminated**: The process has finished execution.



Diagram of Process State





Process Control Block (PCB)

Information associated with each process.

- Process state
- Program counter
- CPU registers
- CPU scheduling information
- Memory-management information
- Accounting information
- I/O status information




Process Control Block (PCB)

pointer	process state
process number	
program counter	
registers	
memory limits	
list of open files	
• • •	



CPU Switch From Process to Process






Process Scheduling Queues

- Job queue – set of all processes in the system.
- Ready queue – set of all processes residing in main memory, ready and waiting to execute.
- Device queues – set of processes waiting for an I/O device.
- Process migration between the various queues.




Ready Queue And Various I/O Device Queues





Representation of Process Scheduling






Schedulers

- Long-term scheduler (or job scheduler) – selects which processes should be brought into the ready queue.
- Short-term scheduler (or CPU scheduler) – selects which process should be executed next and allocates CPU.



Addition of Medium Term Scheduling





Schedulers (Cont.)

- Short-term scheduler is invoked very frequently (milliseconds) \Rightarrow (must be fast).
- Long-term scheduler is invoked very infrequently (seconds, minutes) \Rightarrow (may be slow).
- The long-term scheduler controls the *degree of multiprogramming*.
- Processes can be described as either:
 - *I/O-bound process* – spends more time doing I/O than computations, many short CPU bursts.
 - *CPU-bound process* – spends more time doing computations; few very long CPU bursts.



Context Switch

- When CPU switches to another process, the system must save the state of the old process and load the saved state for the new process.
- Context-switch time is overhead; the system does no useful work while switching.
- Time dependent on hardware support.



Process Creation

- Parent process create children processes, which, in turn create other processes, forming a tree of processes.
- Resource sharing
 - Parent and children share all resources.
 - Children share subset of parent's resources.
 - Parent and child share no resources.
- Execution
 - Parent and children execute concurrently.
 - Parent waits until children terminate.




Process Creation (Cont.)

- Address space
 - Child duplicate of parent.
 - Child has a program loaded into it.
- UNIX examples
 - **fork** system call creates new process
 - **exec** system call used after a **fork** to replace the process' memory space with a new program.



Processes Tree on a UNIX System





Process Termination

- Process executes last statement and asks the operating system to decide it (**exit**).
 - Output data from child to parent (via **wait**).
 - Process' resources are deallocated by operating system.
- Parent may terminate execution of children processes (**abort**).
 - Child has exceeded allocated resources.
 - Task assigned to child is no longer required.
 - Parent is exiting.
 - Operating system does not allow child to continue if its parent terminates.
 - Cascading termination.



UNIT 4

CPU Scheduling




Basic Concepts

- Maximum CPU utilization obtained with multiprogramming
- CPU-I/O Burst Cycle – Process execution consists of a *cycle* of CPU execution and I/O wait.
- CPU burst distribution




Alternating Sequence of CPU And I/O Bursts





Histogram of CPU-burst Times





CPU Scheduler

- Selects from among the processes in memory that are ready to execute, and allocates the CPU to one of them.
- CPU scheduling decisions may take place when a process:
 1. Switches from running to waiting state.
 2. Switches from running to ready state.
 3. Switches from waiting to ready.
 4. Terminates.
- Scheduling under 1 and 4 is *nonpreemptive*.
- All other scheduling is *preemptive*.



Dispatcher

- Dispatcher module gives control of the CPU to the process selected by the short-term scheduler; this involves:
 - switching context
 - switching to user mode
 - jumping to the proper location in the user program to restart that program
- *Dispatch latency* – time it takes for the dispatcher to stop one process and start another running.



Scheduling Criteria

- CPU utilization – keep the CPU as busy as possible
- Throughput – # of processes that complete their execution per time unit
- Turnaround time – amount of time to execute a particular process
- Waiting time – amount of time a process has been waiting in the ready queue
- Response time – amount of time it takes from when a request was submitted until the first response is produced, **not** output (for time-sharing environment)



Optimization Criteria


- Max CPU utilization
- Max throughput
- Min turnaround time
- Min waiting time
- Min response time



First-Come, First-Served (FCFS) Scheduling

<u>Process</u>	<u>Burst Time</u>
P_1	24
P_2	3
P_3	3

- Suppose that the processes arrive in the order: P_1, P_2, P_3
The Gantt Chart for the schedule is:




- Waiting time for $P_1 = 0$; $P_2 = 24$; $P_3 = 27$ 30
- Average waiting time: $(0 + 24 + 27)/3 = 17$



FCFS Scheduling (Cont.)

Suppose that the processes arrive in the order



- Waiting time for $P_1 = 6$; $P_2 = 0$; $P_3 = 3$
- Average waiting time: $(6 + 0 + 3)/3 = 3$
- Much better than previous case.
- *Convoy effect* short process behind long process




Shortest-Job-First (SJR) Scheduling

- Associate with each process the length of its next CPU burst. Use these lengths to schedule the process with the shortest time.
- Two schemes:
 - nonpreemptive – once CPU given to the process it cannot be preempted until completes its CPU burst.
 - preemptive – if a new process arrives with CPU burst length less than remaining time of current executing process, preempt. This scheme is known as the Shortest-Remaining-Time-First (SRTF).
- SJF is optimal – gives minimum average waiting time for a given set of processes.



Example of Non-Preemptive SJF

<u>Process</u>	<u>Arrival Time</u>	<u>Burst Time</u>
P_1	0.0	7
P_2	2.0	4
P_3	4.0	1
P_4	5.0	4




- Average waiting time = $(0 + 6 + 3 + 7) / 4 - 4$



Example of Preemptive SJF

<u>Process</u>	<u>Arrival Time</u>	<u>Burst Time</u>
P_1	0.0	7
P_2	2.0	4
P_3	4.0	1
P_4	5.0	4



- Average waiting time = $(9 + 1 + 0 + 2) / 4 - 3$



Determining Length of Next CPU Burst

- Can only estimate the length.
- Can be done by using the length of previous CPU bursts, t_n , using exponential averaging.
 t_n = actual length of n^{th} CPU burst
 1. τ_n = predicted value for the next CPU burst
 2. τ_{n+1} = predicted value for the next CPU burst
 3. $\alpha, 0 \leq \alpha \leq 1$
 4. Define:

$$\tau_{n+1} = \alpha t_n + (1 - \alpha)\tau_n.$$